Framework Apron

by Heather Seth & Elise Lea for White Owl Textiles Oven Mitt: 6½" x 9½" Pot Holder:: 7½" x 9½"


















Fabric Guide




Main

1/3 yard



Lining/Pocket ¹/₃ yard



BindingFat Quarter

Additional Supplies:

100% Cotton Batting (no polyester)
Insul-Bright or other heat resistant batting

Kindly note, our free patterns are not to be sold nor hosted on any other websites. We appreciate your understanding.

All seam allowances are ¼" unless otherwise stated. Press seams open unless otherwise stated. WOF = Width of Fabric (selvage to selvage)

RST = Right Sides Together WST = Wrong Sides Together

Cutting Instructions

Main	Cut one piece 11" x 20" for oven mitt main Cut two pieces 11" x 10" for pot holder main
Lining/ Pocket	Cut one piece 11" x 20" for oven mitt lining Cut two pieces 7½" x 7½" for pot holder pocket
Binding	 Cut one piece 2½" x LOF - subcut one 2½" x 11" strip for binding trim remainder down to 2" wide and cut one 2" x 5" strip for oven mitt hanging loop Cut one piece 2½ x LOF - subcut 1 strip 2½" x 8" for pot holder pocket binding trim remainder down to 2" wide and cut one 2" x 5" strip for pot holder hanging loop From remainder, using your favorite bias binding technique, cut a total of 46" of 2½" bias binding
Cotton Batting	Cut two pieces 11" x 20" for oven mitt Cut two pieces 11" x 10" for pot holder
Insul-Bright	Cut one piece 11" x 20" for oven mitt Cut one piece 11" x 10" for pot holder

Template Instructions

Print pages 6 and 7 at 100%. Do not fit to page or scale to fit.

Measure the 1" test square to make sure it measures 1".

Cut the templates out along the lines.

Oven Mitt Instructions


Step 1: Layer the following 11" x 20" oven mitt pieces:

- 1. Oven mitt lining wrong side up
- 2. 11" x 20" 100% Cotton batting
- 3. 11" x 20" Insul-Bright,
- 4. 11" x 20" 100% Cotton batting
- 5. Oven mitt main right side up.





Quilt as desired to secure all the layers together.

Step 2: Using the templates cut out 2 oven mitts one with the template facing up and one with the template facing down so they are mirror images of each other.



Step 3: Place the two oven mitts right sides together with the main on the inside and lining on the outsides. Sew around the oven mitt using a %" seam allowance, leaving the bottom edge unsewn.





to about %" away from the seam allowince to seperate the thumb. Trim seam allowance down to a ¼" and zizag raw edges if desired. Turn right side out.

Step 4: To make the hanging loop, fold a 2" x 5" binding strip in half the long way wrong sides together and press.



Open the strip up and fold the edges of the hanging loop in to the middle creased line and press.




Fold the strap in half again along the original fold line. Press. Topstitch along both edges of the hanging loop about an 1/8" away from the edge.



Oven Mitt Instructions

Step 5: Fold the hanging loop in half (twisting one side once if desired) and pin it in place on the oven mitt outer seam, lining up raw edges as shown.


Baste in place ½" from the edge.




Step 6: Fold the $2\frac{1}{2}$ " x 11" binding strip in half WST. Press.




Open it back up and fold the strip in half RST lining up the short ends. Sew along the short end with a 1/4" seam allowance to make a loop. Press seam to the side.




Refold along original fold line WST so the raw edges line up and press again if needed.



Step 7: Pull the binding loop over the outside of the oven mitt, lining up the raw edges of the binding with the raw edges of the oven mitt and pin in place. Stitch through the binding and mitt all the way around the opening.



Step 8: Fold the Binding around the seam allowance and into the lining of the oven mit. Stitch in place along the edge.



Woohoo! Your Oven Mitt is now finished!


Pot Holder Instructions

Step 1: Layer the following 11" x 20" pot holder pieces:


- 1. Pot holder main wrong side up
- 2. 11" x 10" 100% Cotton batting
- 3. 11" x 10" Insul-Bright,
- 4. 11" x 10" 100% Cotton batting
- 5. Pot holder main right side up.

Quilt as desired to secure all the layers together.


Step 2: Using the templates cut out 1 pot holder. Zig-zag edges if desired.




Step 3: Place the two $7\frac{1}{2}$ " x $7\frac{1}{2}$ pockets WST. Take the $2\frac{1}{4}$ " x 8" binding strip and fold it in half the long way WST. Press. Line up the raw edges of the binding with the top edge of the pockets RST and stitch a $1\frac{1}{4}$ " away from the edge.



Fold the binding up and press. Fold binding up and over the raw edges and onto the backside of the pocket. Stitch binding down 1/8" from the edge. Trim excess binding so the edges are square with the pocket.



Step 4: Lay the pocket on top of the pot holder, lining up the bottom and side edges (the corners of the pocket will stick out). Baste in place 1/8" from the edge. Trim corners of pocket to match the shape of the pot holder main.



Pot Holder Instructions

Step 5: Make a hanging loop using the same method as in Step 4 of the oven mitt pattern.


In the top center of the oven mitt, line the raw edges of the hanging loop with the raw edges of the oven mitt, twisting the hanging loop once if desired to get the loop to lay more flat.




Step 6: Bind the pot holder using bias binding, making sure to stitch down the hanging loop and the front pocket.



Woohoo! Your Pot Holder is now finished!





Stripes and Stars



Fabric Guide



Main W140-005-035 ¹/₃ yard



Lining/Pocket W140-004-535 1/3 yard



Binding W140-009-590 Fat Quarter

Additional Supplies:

100% Cotton Batting (no polyester)
Insul-Bright or other heat resistant batting

Coffee and Co





Fabric Guide



Main W135-006-030 ¹/₃ yard



Lining/Pocket W135-008-063 1/3 yard



Binding W135-009-370 Fat Quarter

Additional Supplies:

100% Cotton Batting (no polyester)
Insul-Bright or other heat resistant batting

Sweet Honey Bee



Fabric Guide



Main W115-004-863 ¹/₃ yard



Lining/Pocket W115-010-041 1/3 yard



Binding W130-001-405 Fat Quarter

Additional Supplies:

100% Cotton Batting *(no polyester)* Insul-Bright or other heat resistant batting